

Install Fedora Core OS (FCOS)

create the ignite file

you do this by creating a butane config yaml and converting it to an ignite json using butane.

install butane on a fedora workstation

```
dnf install -y butane
```

create the butane config file

Create a yaml file with your config, mind the indentation. In this example only a group and a user with a specific uid is created (an exhaustive list of the options for butane config can be found [here](#)) i name this file *version1.bu*

```
version: 1.6.0
passwd:
  groups:
    - name: beheerders
      gid: 700
  users:
    - name: abel
      uid: 700
      primary_group: users
      groups:
        - beheerders
      ssh_authorized_keys:
        - ssh-ed25519 AAAAC3.....P abel@nergens
```

convert the butane file to an ignite file

Then with butane transform it to the ignite json: `butane --pretty --strict version1.bu > version1.ign`

the resulting json file *version1.ign* looks like:

```
{
  "ignition": {
    "version": "3.5.0"
  },
  "passwd": {
    "groups": [
      {
```

```
        "gid": 700,  
        "name": "beheerders"  
    },  
    ],  
    "users": [  
        {  
            "groups": [  
                "beheerders"  
            ],  
            "name": "abel",  
            "primaryGroup": "users",  
            "sshAuthorizedKeys": [  
                "ssh-ed25519 AAAAC3N.....P abel@nergens"  
            ],  
            "uid": 700  
        }  
    ]  
}
```

create an USB installation disk

download Fedora Core OS

Download the fedora coreos image from :

https://fedoraproject.org/coreos/download?stream=stable&arch=x86_64

and create a bootable installation medium USB stick using *dd* or *Rufus*

add the ignite file

copy the previously made ignite file to the USB disk you just made.

boot and install the target baremetal server

stick the USB install disk in the server, turn on and in the BIOS or in the bootmenu choose the USB device as boot device.

once the system is booted on the prompt enter:

```
lsblk
```

and choose the disk to install to (in this example `/dev/sda`). Then start the installation :

```
sudo coreos-installer install /dev/sda --ignition-file version1.ign
```

sources

<https://www.flatcar.org/docs/latest/provisioning/config-transpiler/configuration/>

<https://docs.fedoraproject.org/en-US/fedora-coreos/bare-metal/>

further reading:

<https://www.redhat.com/en/blog/red-hat-enterprise-linux-coreos-customization>

From:
<https://wiki.auriel.nl/> -

Permanent link:
https://wiki.auriel.nl/doku.php?id=installatie_handleidingen:fedora-coreos&rev=1756817732



Last update: **2025/09/02 14:55**